
COS 217: Introduction to Programming Systems

Virtual Memory, Storage Hierarchy, and Caching



Agenda





Processes

Program

- Executable code
- A static entity

Process

- An instance of a program in execution
- A dynamic entity: has a time dimension
- Each process runs one program
 - E.g. the process with Process ID 12345 might be running emacs
- One program can run in multiple processes
 - E.g. PID 12345 might be running emacs, and PID 23456 might also be running emacs for the same user or for a different user






1. Processes believe they have *private control flow* (i.e., they own the whole CPU, all the time)

 Processes believe they have a private address space (i.e., they own all the memory that the machine has or could have)

Process is a profound abstraction in computer science

Private Address Space: Illusion






Each process sees main memory as

Huge: 2^{64} = 16 EB (16 exabytes) of memory $\approx 10^{19}$ bytes Uniform: contiguous memory locations from 0 to 2^{64} -1

Private Address Space: Reality





Memory is divided into pages

- At any time, some pages are in physical memory, some on disk (\approx in a file)
- OS and hardware swap pages between physical memory and disk
- Multiple processes share physical memory

Virtual & Physical Addresses

Question

• How do OS and hardware implement virtual memory?

Answer (part 1)

• Distinguish between virtual addresses and physical addresses



Virtual & Physical Addresses (cont.)

Virtual address

virtual page num offset

- Identifies a location in a particular process's virtual memory
 - Independent of size of physical memory
 - Independent of other concurrent processes
- Consists of virtual page number & offset
- Used by application programs

Physical address

physical page num offset

- Identifies a location in physical memory
- Consists of physical page number & offset
- Known only to **OS** and **hardware**

Note:

8

• Offset is same in virtual addr and corresponding physical addr



ArmLab Virtual & Physical Addresses



virtual virtua addr	virtual page num		offset
		48 bits	 16 bits
physical addr		physical page num	offset

On ArmLab:

- Each virtual address consists of 64 bits
 - There are 2⁶⁴ bytes of virtual memory (per process)
- Each offset is 16 bits
 - Each page consists of 2¹⁶ bytes
- Each virtual page number consists of 64 16 = 48 bits
 - There are 2⁴⁸ virtual pages

ArmLab Virtual & Physical Addresses



virtual addr	virtual page num		offset
auur	L	48 bits	Left 16 bits
		40 DILS	
physica addr	l	physical page num	offset
addi			JJ
		21 bits	16 bits

On ArmLab:

- Each physical address consists of 37 bits
 - There are 2³⁷ (128G) bytes of physical memory (per computer)
- Each offset is 16 bits
 - Each page consists of 2¹⁶ bytes
- Each physical page number consists of 37 16 = 21 bits
 - There are 2²¹ physical pages





Question

11

• How do OS and hardware implement virtual memory?

Answer (part 2)

• Maintain a page table for each process (stored in physical memory)

Page Tables (cont.)



Page Table for Process 1234

Virtual Page Num	Physical Page Num or Disk Addr
0	Physical page 5
1	(unmapped)
2	Spot X on disk
3	Physical page 8

. . .

. . .

12

Page table maps each in-use virtual page to:

- A physical page, or
- A spot on disk

Storing Page Tables

Question

• Where are the page tables themselves stored?

Answer

• In main memory

Question

• What happens if a page table is swapped out to disk???!!!

Answer

- It hurts! So don't do that, then!
- OS is responsible for swapping
- Special logic in OS "pins" page tables to physical memory
 - So they never are swapped out to disk





Question

14

• How do OS and hardware implement virtual memory?

Answer (part 3)

• Trigger a page fault for accesses to virtual pages that are swapped out (on disk)

Page Faults




- Process executes instruction that references virtual memory
- CPU determines virtual page
- CPU checks if required virtual page is in physical memory: no!
 - CPU generates page fault
 - OS gains control of CPU
 - OS (potentially) evicts some page from physical memory to disk, loads required page from disk to physical memory
 - OS returns control of CPU to process to same instruction
- Process executes instruction that references virtual memory
- CPU checks if required virtual page is in physical memory: yes
- CPU does load/store from/to physical memory

Virtual memory enables the illusion of private address spaces



VM Effects on Security and Speed

Q: What effect does virtual memory have on the security and speed of processes?



Let's start by considering security...

Memory protection among processes

- Process's page table references only physical memory pages that the process currently owns
- Process can't accidentally/maliciously affect physical memory used by another process

Memory protection within processes

- Permission bits in page-table entries indicate whether page is read-only, etc.
- Allows CPU to prohibit

- Writing to RODATA & TEXT sections
- Access to protected (OS owned) virtual memory




18

VM Effects on Security and Speed



Q: What effect does virtual memory have on the security and speed of processes?



OK, so part of the answer is:

Security



But what about speed?

Revisiting Page Tables...



Question

• Doesn't each logical memory access require **two** physical memory accesses – one to access the page table, and one to access the desired datum?

Answer

• Conceptually, yes!

(And page tables are stored hierarchically as trees, so it can be even worse than 2 accesses!)

Question


• Isn't that inefficient?

Answer


• Conceptually: yes, but in actuality not really ... let's see why!

Agenda









Factors to consider:


- Capacity
- Latency (how long to do a read)
- Bandwidth (how many bytes/sec can be read)
 - Weakly correlated to latency: reading 1 MB from a hard disk isn't much slower than reading 1 byte
- Volatility
 - Do data persist in the absence of power?

Registers

- Latency: 0 cycles
- Capacity: 8-256 registers (31 8-byte general purpose registers in AArch64)
- L1/L2/L3 Cache
 - Latency: 1 to 40 cycles
 - Capacity: 32KB to 32MB

Main memory (RAM)

- Latency: ~ 50-100 cycles
 - 100 times slower than registers
- Capacity: GB







Local secondary storage: disk drives

- Solid-State Disk (SSD):
 - Flash memory (nonvolatile)
 - Latency: 0.1 ms (~ 300k cycles)
 - Capacity: 128 GB several TB
- Hard Disk:
 - Spinning magnetic platters, moving heads
 - Latency: 10 ms (~ 30M cycles)
 - Capacity: 1 dozens of TB









Cache / RAM Latency






1 clock = 3-10⁻¹⁰ sec <u>https://www.anandtech.com/show/6993/intel-iris-pro-5200-graphics-review-core-i74950hq-tested/3</u>



Remote secondary storage (a.k.a. "the cloud")

- Latency: tens of milliseconds
 - Limited by the speed of light (and network bandwidth)
- Capacity: essentially unlimited





Storage Device Speed vs. Size

Facts:

- CPU needs sub-nanosecond access to data to run instructions at full speed
- Fast storage (sub-nanosecond) is small (100-1000 bytes)
- Big storage (gigabytes) is slow (15 nanoseconds)
- Huge storage (terabytes) is glacially slow (milliseconds)

Goal:

- Need many gigabytes of memory,
- but with fast (sub-nanosecond) average access time

Solution: locality allows caching

- Most programs exhibit good locality
- A program that exhibits good locality will benefit from proper caching, which enables good average performance

Locality



Two kinds of **locality**

- Temporal locality
 - If a program references item X now, then it probably will reference X again soon
- Spatial locality
 - If a program references item X now, then it probably will reference item at address $X \pm 1$ soon

Most programs exhibit good temporal and spatial locality

30


Temporal locality

Locality example

- *Data:* Whenever the CPU accesses sum, it accesses sum again shortly thereafter
- Instructions: Whenever the CPU executes sum += a[i], it executes sum += a[i] again shortly thereafter

Spatial locality

- *Data:* Whenever the CPU accesses a[i], it accesses a[i+1] shortly thereafter
- *Instructions:* Whenever the CPU executes sum += a[i],
- it executes i++ (which are the next machine language instructions) shortly thereafter



Typical code (good overall locality)





Caching



Cache


- Fast access, small capacity storage device
- Acts as a staging area for a subset of the items in a slow access, large capacity storage device

Good locality + proper caching

- \Rightarrow Most storage accesses can be satisfied by cache
- \Rightarrow Overall storage performance improved

Caching in a Storage Hierarchy





Cache Hits and Misses

Cache hit


- E.g., request for block 10
- Access block 10 at level k
- Fast!

Cache miss

- E.g., request for block 8
- Evict some block from level k
- Load block 8 from level k+1 to level k
- Access block 8 at level k
- Slow!

Caching goal:

- Maximize cache hits
- Minimize cache misses








VM Effects on Security and Speed



Q: What effect does virtual memory have on the security and speed of processes?



So, with caching, we *finally* arrive at the answer:

Security

Speed



often little or no change

Agenda



Virtual vs. physical memory **Virtual Memory** Page tables Page faults The storage hierarchy Storage and Locality Spatial and temporal locality Caching Block size **Effective Caching** Eviction policy 35 Order of operations





Here's a real question from an old exam:

For caching in a memory hierarchy,

what is the best motivation for a *larger* cache block size?

- A. Temporal Locality
- B. Spatial Locality
- C. Both
- D. Neither

В

Spatial locality makes use of subsequent data after a given read, so having more data to keep reading is a win. Cache Block Size

Large block size:

- + do data transfer less often
- + take advantage of spatial locality
- longer time to complete data transfer
- less advantage of temporal locality

Small block size: the opposite

Typical: Lower in pyramid \Rightarrow slower data transfer \Rightarrow larger block sizes

Device	Block Size
Register	8 bytes
L1/L2/L3 cache line	128 bytes
Main memory page	4KB or 64KB
Disk block	512 bytes to 4KB
Disk transfer block	4KB (4096 bytes) to 64MB (67108864 bytes)

Cache Management



Device	Managed by:
Registers (cache of L1/L2/L3 cache and main memory)	Compiler, using complex code- analysis techniques Assembly lang programmer
L1/L2/L3 cache (cache of main memory)	Hardware, using simple algorithms
Main memory (cache of local sec storage)	Hardware and OS, using virtual memory with complex algorithms (since accessing disk is expensive)
Local secondary storage (cache of remote sec storage)	End user, by deciding which files to download

Cache Eviction Policies

Best eviction policy: "oracle"

- Always evict a block that is *never* accessed again, or...
- Always evict the block accessed the furthest in the future
- Impossible in the general case

Worst eviction policy

- Always evict the block that will be accessed next!
- Causes thrashing
- Impossible in the general case!

Reasonable eviction policy: LRU policy

- Evict the "Least Recently Used" (LRU) block
 - With the assumption that it will not be used again (soon)
- Good for straight-line code
- (can be) bad for (large) loops
- Expensive to implement

- Often simpler approximations are used
- See Wikipedia "Page replacement algorithm" topic



Locality/Caching Example: Matrix Multiplication

Matrix multiplication

41

- Matrix = two-dimensional array
- Multiply n-by-n matrices A and B
- Store product in matrix C

Performance depends upon

- Effective use of caching (as implemented by **system**)
- Good locality (as implemented by you)

Locality/Caching Example: Matrix Multiplication



Two-dimensional arrays are stored in either **row-major** or **column-major** order

а	0	1	2
0	18	19	20
1	21	22	23
2	24	25	26

row-major		r col-major		
a[0][0]	18	a[0][0]	18	
a[0][1]	19	a[1][0]	21	
a[0][2]	20	a[2][0]	24	
a[1][0]	21	a[0][1]	19	
a[1][1]	22	a[1][1]	22	
a[1][2]	23	a[2][1]	25	
a[2][0]	24	a[0][2]	20	
a[2][1]	25	a[1][2]	23	
a[2][2]	26	a[2][2]	26	

C uses row-major order

- Access in row order \Rightarrow good spatial locality
- Access in column order \Rightarrow poor spatial locality






for (i=0; i<n; i++)
for (j=0; j<n; j++)
for (k=0; k<n; k++)
c[i][j] += a[i][k] * b[k][j];</pre>

Reasonable cache effects

- Good locality for A
- Bad locality for B
- Good locality for C








for (j=0; j<n; j++) for (k=0; k<n; k++) for (i=0; i<n; i++) c[i][j] += a[i][k] * b[k][j];

Poor cache effects

- Bad locality for A
- Bad locality for B
- Bad locality for C








for (i=0; i<n; i++) for (k=0; k<n; k++) for (j=0; j<n; j++) c[i][j] += a[i][k] * b[k][j];


Good cache effects

- Good locality for A
- Good locality for B
- Good locality for C



Next time ...





Lobsterthermidor , Raysonho